

BLUE Open Studio OMNEP Driver

Driver Version 1.0

Release Notes

BOS-OMNEP-RN-EN.00
1/2025

Legal Information

The information provided in this document contains general descriptions, technical characteristics and/or recommendations related to products/solutions.

This document is not intended as a substitute for a detailed study or operational and site-specific development or schematic plan. It is not to be used for determining suitability or reliability of the products/solutions for specific user applications. It is the duty of any such user to perform or have any professional expert of its choice (integrator, specifier or the like) perform the appropriate and comprehensive risk analysis, evaluation and testing of the products/solutions with respect to the relevant specific application or use thereof.

The Pro-face brand and any trademarks of Schneider Electric SE and its subsidiaries referred to in this document are the property of Schneider Electric SE or its subsidiaries. All other brands may be trademarks of their respective owner.

This document and its content are protected under applicable copyright laws and provided for informative use only. No part of this document may be reproduced or transmitted in any form or by any means (electronic, mechanical, photocopying, recording, or otherwise), for any purpose, without the prior written permission of Schneider Electric.

Schneider Electric does not grant any right or license for commercial use of the document or its content, except for a non-exclusive and personal license to consult it on an "as is" basis.

Schneider Electric reserves the right to make changes or updates with respect to or in the content of this document or the format thereof, at any time without notice.

To the extent permitted by applicable law, no responsibility or liability is assumed by Schneider Electric and its subsidiaries for any errors or omissions in the informational content of this document, as well as any non-intended use or misuse of the content thereof.

Contents

- Safety Information4
 - Safety Symbols and Terms4
- About the Book5
 - Document Scope.....5
 - Validity Note5
 - Related Documents.....5
 - Information on Non-Inclusive or Insensitive Terminology5
 - Trademarks5
- Product Information6
 - Installation Instructions.....6
 - Release History6

Safety Information

Safety Symbols and Terms

This manual uses the following symbols and terms to identify important information related to the correct and safe operation of display unit and screen editing software.




The symbols and the descriptions are as follows:



The addition of this symbol to a "Danger" or "Warning" safety label indicates that an electrical hazard exists which will result in personal injury if the instructions are not followed.



This is the safety alert symbol. It is used to alert you to potential personal injury hazards. Obey all safety messages that follow this symbol to avoid possible injury or death.

<div> DANGER</div> <div>DANGER indicates a hazardous situation which, if not avoided, will result in death.</div>
<div> WARNING</div> <div>WARNING indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury.</div>
<div> CAUTION</div> <div>CAUTION indicates a potentially hazardous situation which, if not avoided, could result in minor or moderate injury.</div>
<div><i>NOTICE</i></div> <div><i>NOTICE</i> is used to address practices not related to physical injury.</div>

About the Book

Document Scope

This document contains important information about the delivery of BLUE Open Studio OMNEP driver, and the history of previous releases.

Read this document completely before using the product or products described.

Validity Note

This document is valid for BLUE Open Studio OMNEP driver.

The characteristics of the products described in this document are intended to match the characteristics that are available on www.proface.com. As part of our corporate strategy for constant improvement, we may revise the content over time to enhance clarity and accuracy. If you see a difference between the characteristics in this document and the characteristics on www.proface.com, consider www.proface.com to contain the latest information.

Related Documents

You can download the manuals related to this product from the Pro-face download page (www.pro-face.com/trans/en/manual/1085.html).

Information on Non-Inclusive or Insensitive Terminology

As a responsible, inclusive company, Schneider Electric is constantly updating its communications and products that contain non-inclusive or insensitive terminology. However, despite these efforts, our content may still contain terms that are deemed inappropriate by some customers.

Trademarks

Schneider Electric has made every effort to supply trademark information about company names, products, and services mentioned in this manual.

All other brands and products referenced in this document are acknowledged to be the trademarks or registered trademarks of their respective holders.

Product Information

<Driver Name>: OMNEP

<Description>: OMRON NJ/NX EtherNet/IP CIP Message Communications

Installation Instructions

This driver is valid for BLUE Open Studio version 2023.1 only.

1. Exit BLUE Open Studio editor and runtime.
2. Unzip the downloaded communication driver zip file and extract the following files.
 - <DriverName>.ini
 - <DriverName>.msg
 - <DriverName>.dll
 - <DriverName>.pdf
3. Copy the four unzipped files into the folder below.
<Folder where Blue Open Studio is installed>\Drv

NOTE: The default installation location is *C:\Program Files (x86)\Pro-face\BLUE Open Studio 2023\Drv*.

Release History

Version	Release Date	Description
V1.0	Jan. 24, 2025	Initial version

Schneider Electric Japan Holdings Ltd.

4-4-9 Kitahama, Chuo-ku, Osaka

541-0041

Japan

+ 81 (0) 50 4561 4800

www.proface.com

As standards, specifications, and design change from time to time,
please ask for confirmation of the information given in this
publication.

© 2025 - Schneider Electric Japan Holdings Ltd. All rights reserved.

BOS-OMNEP-RN-EN.00